






# Introduction to LabVIEW for FRC

April Riddett  
Applications Engineer

110  
Countries  
7000+  
Universities




# The LabVIEW Continuum



# Companies that use LabVIEW





# FRC LabVIEW Quick Start Guide

## Setup

## NI LabVIEW Basics

- Software Setup Overview
- FRC Software Orientation
- roboRIO Introduction and Set Up
- Basics of the Robot Project
- Deploying and Driving

# FRC Software Overview

## NI Software for FRC

- LabVIEW
- LabVIEW Real-Time
- Vision Development Module
- IMAQdx (vision driver)
- NI-RIO (roboRIO driver)
- FRC Simulation Viewer



Included in Kit of Parts  
or  
Download at [ni.com/frc](http://ni.com/frc)

## FRC Update Suite

- Driver Station
- roboRIO Utilities
- WPI Library
- FRC LabVIEW Templates
- FRC LabVIEW Examples


Required for ALL FRC Teams  
Download Only

All download links available at [ni.com/frc](http://ni.com/frc).



## 2. Activate

- Activate LabVIEW using the serial number on the back of the DVD envelope.



NI Software for FRC 2015

Serial Starts with M

NI LabVIEW for FRC 2015

User Information  
Enter the following information.

Full Name:

Organization:

Install NI LabVIEW for FRC 2015 using the following serial number:

Serial Number:

Leave the Serial Number field blank to use the product in evaluation mode.

<< Back Next >> Cancel

### 3. Install FRC 2017 Update Suite


All teams must install the Update Suite.

Install Update after LabVIEW

#### Install Components

LabVIEW Teams : Everything


Java/C Teams: Driver Station & Utilities



### 3. Install FRC 2015 Update Suite

All teams must install the Update Suite.

Activate with the same serial number  
from the DVD Envelope



The screenshot shows a window titled "FRC 2015 Update Suite" with a blue header bar containing the National Instruments logo. Below the header, the text "User Information" is followed by "Enter the following information." The form contains three input fields: "Full Name:" with the value "Hunter Smith", "Organization:" with the value "Team 2468", and "Serial Number:" which is empty. Below the "Serial Number:" field, there is a note: "Leave the Serial Number field blank to use the product in evaluation mode." At the bottom of the window, there are three buttons: "<< Back", "Next >>", and "Cancel".

FRC 2015 Update Suite

**User Information**  
Enter the following information.

Full Name:

Organization:

Install FRC Driver Station using the following serial number:


Serial Number:

Leave the Serial Number field blank to use the product in evaluation mode.

<< Back   Next >>   Cancel


# Software Orientation: Getting Started Window

This window opens when you start FRC LabVIEW.




# Software Orientation: Getting Started Window

This window opens when you start FRC LabVIEW.



# Software Orientation: roboRIO Robot Project

- With the LabVIEW project window, you can see all of the code that will run on your robot. The FRC software includes a template project with everything you need to start.



# Software Orientation: Driver Station

The Driver Station is the robot control utility for practice and competition for all FRC teams. Open this to connect to your robot and run your code you wrote.

The screenshot shows the FRC Driver Station - Version 15.0b49 interface. It features a sidebar on the left with icons for different functions. The main area is divided into several sections:

- Operation Tab:** A callout pointing to the left sidebar.
- Mode:** A callout pointing to the 'TeleOperated', 'Autonomous', 'Practice', and 'Test' buttons.
- Robot Info Section:** A callout pointing to the 'Team # 2468', 'Simulated Robot', 'Communications', 'Robot Code', 'Joysticks', 'Autonomous Disabled', and 'Window' controls.
- Messages Mode:** A callout pointing to the 'Messages Mode' button on the right sidebar.

Below the 'Robot Info Section' callout, a note states: "All lights should be green to run".

# Software Orientation: Driver Station

Diagnostics  
Tab

Error Messages

The screenshot displays the FRC Driver Station software interface, version 15.0b49. The interface is divided into several sections:


- Left Sidebar:** Contains icons for various system components: a steering wheel (Diagnostics), a robot (Robot), a gear (Settings), a USB symbol (USB), and a lightning bolt (Power).
- Communications Section:** Lists connection methods: Enet Link, DS Radio, Bridge, Robot, and FMS.
- Versions Section:** Displays version information for DS (07.01.13.00), RIO, and Lib.
- Team # 2468:** Shows the team number.
- Simulated Robot:** Includes status indicators for Communications, Robot Code, and Joysticks, all shown as green bars.
- Teleoperated Enabled:** A status indicator.
- Reboot/Restart Buttons:** Two buttons labeled "Reboot roborIO" and "Restart Robot Code" are located below the Communications section.
- Free RAM (MB): 0**  
**Free Disk (MB): 0**
- Error Messages Panel:** A panel on the right titled "Logs ..." showing error messages. The first message is: **ERROR -44061** occurred at "Left and Right Motors" in the VI path: Robot Main.vi. The second message is: **FRC: The loop that contains RobotDrive is not running fast enough.** This error can occur if the loop contains too much code, or if one or more other loops are starving the RobotDrive loop. The third message is: **ERROR -44061** occurred at "Left and Right Motors" in the VI path: Robot Main.vi.

Easily Reboot or  
Restart from the  
dashboard



# Software Orientation: Driver Station

Set Up Tab


Configure Match  
SettingsChart  
Mode

# Software Orientation: Driver Station

USB Devices  
Tab


Live Joystick  
Inputs

Messages &  
Chart Mode



# Software Orientation: Driver Station

## Power & CAN Tab



FRC Driver Station - Version 15.0b49

**Power & CAN Tab**

Tripped Count		Faults		CAN Metrics	
40A	0	Comms	0	Utilization %	0
20/30A	0	12V	0	Bus Off	0
		6V	0	TX Full	0
		5V	0	Receive	0
		3.3V	0	Transmit	0

**Team # 2468**

**Simulated Robot**

- Communications ■
- Robot Code ■
- Joysticks ■

**Autonomous Disabled**


Log: ...

POWERED BY LabVIEW

FIRST

# roboRIO

Controller for FRC 2015-2019



# MXP – myRIO Expansion Port

Create your own expansion board for roboRIO

MXP Developer's Guide: [bit.ly/roboRIO-MXP](http://bit.ly/roboRIO-MXP)

All FRC Teams get a Free License  
for the NI Circuit Suite




Multisim Circuit  
SPICE &  
Simulation

Ultiboard PCB  
Design &  
Layout



Be sure to check the official rules  
from FIRST to make sure your  
accessories are competition legal



MXP I/O

10 PWM / DIO

I2C / SPI /

UART

3.3V / 5V / GND



2 Analog

Outputs

4 Analog Inputs

# MXP Accessories

Adaptors and prototyping tools






Available from  
AndyMark

Create a roboRIO accessory? Let us know @NIFIRSTRobotics

# roboRIO Set Up

1. Install the FRC 2017 Update Suite
2. Connect roboRIO to a power supply
3. Connect roboRIO to your PC over USB
4. Run the roboRIO Imaging Tool




Share your unboxing experience  
using #roboRIO

# Drive a Robot: Step 1

## Open the Template Project

**Step 1:** From the LabVIEW Getting Started window, select **New»FRC roboRIO Robot Project** to create a new roboRIO Robot Project





# Drive a Robot: Step 2

## Configure Your roboRIO Robot Project

**Step 2:** Fill in the New Project dialog box. Give the project a meaningful name, set your team number and pick the type of project you want to make.

Select project type based on your drive style and accessories

Create New FRC Robot Project

Select project name, folder, and IP address

Project name  
2017 Robot Project

Project folder  
C:\Users\ariddet\Documents\LabVIEW Data\2017 Robot Project

Team number  
xxyy

☒ Arcade Drive  
☐ Arcade Drive with Arm  
☐ Mecanum Drive with Arm  
☐ Arcade Drive - Command & Control

Project: Robot Project.lvproj  
My Computer  
RT roboRIO Target (172.22.11.2)  
Support Code  
Team Code  
Autonomous.vi  
Begin.vi  
Disabled.vi  
Finish.vi  
Periodic Tasks.vi  
Robot Global Data.vi  
Teleop.vi  
Test.vi  
Vision Processing.vi  
Robot Main.vi  
Dependencies  
Build Specifications

< Back   Next >   Finish   Cancel   Help

# Drive a Robot: Step 3


## Open the Template Project

**Step 3:** To open **Robot Main.vi**, double-click on it in the project window. The front panel should launch. Select **<Ctrl-E>** to open the block diagram and look at the code.

The code you need to edit is in the Team Code folder

If you add new VIs, be sure they are under the roboRIO target


To drive your robot, open Robot Main



# Drive a Robot: Step 4

## Select a Target


**Step 4:** If you have a roboRIO controller connected, make sure you select it. If you don't have an actual robot to drive around, you can still simulate one. Select the **...lvproj/My Computer** target to open the simulator.



# Driving a Robot: Step 5

## Deploy Code

**Step 5:** Click on the **white run arrow** at the top left of Robot Main. The robot project is deployed to the roboRIO controller/simulator. Once LabVIEW is finished deploying the code, open the Driver Station. The LEDs should all be green. Click **TeleOp** and then **Start**.



# Setup Resources

- Software Setup Guide
  - [LabVIEW Development Suite for FRC 2015](#)
  - [Imaging roboRIO and Windows IP Configuration](#)
  - [Troubleshooting roboRIO Connections](#)
  - [Driver Station Tutorial](#)
  - [Custom Dashboard Tutorial](#)
  - [Robotics Framework Tutorial](#)
  - [Robot Simulation Tutorial](#)
- 
- Forum Support (year round)
    - [ni.com/frc](http://ni.com/frc)
  - Phone Support (during build season only)
    - (866) 511-6285 from 1:00 to 7:00 p.m. (Central Time)

All links  
available at  
[ni.com/frc](http://ni.com/frc)

# FRC LabVIEW Quick Start Guide


## Setup

## NI LabVIEW Basics

- What Is LabVIEW?
- LabVIEW Development Environment
- LabVIEW Programming Fundamentals
- Tools and Troubleshooting
- Teleop and Autonomous Code


# What Is LabVIEW?

- A graphical programming environment used to develop sophisticated measurement, test, and control systems



# Teleop Code


- When modifying the FRC Robot Project template, do **not** modify Robot Main.vi.
- Modify the code within the Team Code folder within the project. This code is called on in Robot Main.vi






# Autonomous Code

- Similar to Teleop, Autonomous executes code by references.




Begin.vi




Autonomous Independent.vi

# Parts of Robot Main.vi




LabVIEW  
Project  
Explorer

Front panel  
(user interface)



Block diagram  
(code)



# LabVIEW Project Explorer


## LabVIEW File Extensions

LabVIEW project—.lvproj

Virtual instrument (VI)—.vi

Custom control—.ctl

**Right-click to connect  
to roboRIO target**



# Parts of a VI: Front Panel


The front panel is the VI's graphical user interface with inputs and outputs.

## Controls (inputs)

buttons,  
knobs, slides...

## Indicators (outputs)

numeric display,  
graphs, LEDs...







# Controls Palette

Right-click on the  
**front panel**  
(not the block  
diagram) to open the  
Controls Palette

Pin to keep open


Search for controls

Browse subpalettes




# Parts of a VI: Block Diagram

- The block diagram is the code for each VI. In LabVIEW, graphical blocks are connected with wires to control the execution.




# Functions Palette




Search for functions  
by name

- Right-click on the **block diagram** (not the front panel) to open the Functions Palette
- Contains the VIs, functions, and constants you use to create the block diagram
- FRC-specific palettes include the WPI Robotics Library, *FIRST* Vision, and PID



# Terminals


- With terminals, you can read and write to front panel controls and indicators.






# Dataflow Programming

- Order of execution is controlled by how the wires are connected
- Each function executes when all of the inputs are ready
- Parallel code executes at the same time




# LabVIEW Toolbar

- The tools you need to run, debug, clean up, and edit your code



# Wires (Data Types)

- Other examples of wires in LabVIEW




- Floating point
- Integer
- Boolean
- String
- Array—note the wire thickness
- Cluster (group of other data types)



# Loops


- Allow the same piece of code to run multiple times
- Exit conditions are different for each

## While Loop



Run until stop  
condition met


## For Loop



Iteration  
counter

# SubVIs

- Double-click a subVI to open it
- Use the connector pane to connect controls and indicators



Connector  
pane


Left and Right Motors

Joystick 0

Joystick 0/Axes

Joystick 0/Buttons


Publish the Robot Drive M  
values to the dashboard



# LabVIEW Programming Demonstration


## Programming Demonstration

- Front panel/block diagram
- Tools/functions palettes
- Controls/terminals
- Wiring
- Constants
- Dropping functions
- Run/run continuously
- Loops
- Data types
- Highlight execution




# How Do I Make Decisions in LabVIEW?


## Case Structures



(a)




(b)



(c)

## Select




# Introduction to Clusters

- Data structure that groups data together
- Data may be of different types
- Elements must be either all controls or all indicators
- Thought of as wires bundled into a cable

Easier to bundle wires together and pass around as a group than wire each individually


- **Use Unbundle By Name/Bundle By Name**






# Cluster Functions

- In the Cluster & Variant subpalette of the Programming functions palette
- Can also be accessed by right-clicking the cluster terminal



# Shift Register: Access Previous Loop Data



- Available at left or right border of loop structures
- Right-click the border and select Add Shift Register
- Right terminal stores data on completion of iteration
- Left terminal provides stored data at beginning of next iteration



# Context Help

- Displays basic information about wires and nodes when you hover over with your mouse
- Turn context help on/off
  - Click the yellow ? on the top right corner of your VI
  - Press <Ctrl-H>
  - Select **Help»Show Context Help** from the LabVIEW menu


Click ? to open  
context help



Click for more  
info

# LabVIEW Help



- Contains detailed descriptions and instructions for most palettes, menus, tools, VIs, and functions.
- Open LabVIEW Help by
  - Selecting **Help»LabVIEW Help** from the menu
  - Clicking the **Detailed help** link in the **Context Help** window
  - Right-clicking an object and selecting **Help** from the shortcut menu
  - Pressing **F1**



# Find Examples

- Find FRC templates in the Support Tab»Find FRC Examples...
- Or Help»Find Examples and browse to the FRC Robotics Folder

Search by  
keyword




# Debugging: Correcting Broken VIs

Broken Run arrow » VI cannot be compiled » VI cannot be executed



Click to  
open  
Error List





# Debugging: Probes



- Use the Probe tool to observe intermediate data values and check the error output of VIs and functions, especially those performing I/O.



- Specify to retain the values in the wires so that you can probe wires for data after execution.











# Learn Your Hotkeys

## **LabVIEW™ Quick Reference Guide**










### Keyboard Shortcuts

File		Ctrl-X	Cut object	Right Click	Display controls/ functions palette
Ctrl-N	Create new VI	Ctrl-Z	Undo last action	Shift-Right Click	Display tools palette
Ctrl-S	Save VI	Ctrl-Shift-Z	Redo last action	Ctrl-T	Tile block diagram and front panel windows
Ctrl-P	Print	Operate		Help	
Edit		Ctrl-R	Run VI	Ctrl-H	Display context help
Ctrl-V	Paste object	Ctrl-.	Abort VI		
Ctrl-U	Clean up diagram	Window			
Ctrl-Space	Activate quick drop	Ctrl-E	Display block diagram/ front panel		
Ctrl-B	Remove broken wires				
Ctrl-C	Copy an object				











### Editing Tools

Tool	Icon	Description
Show Context Help		Display the context help window
Text Settings		Change the font setting for the VI, including size, style, and color
		15pt Application Font
Align Objects		Align selected objects
Distribute Objects		Space objects evenly
Resize Objects		Resize multiple front panel objects to the same size
Reorder		Reorder the layers of the objects
Clean Up Diagram		Rearrange wires and objects on the block diagram
Enter		Appears when a new value is available to replace an old value

### Debugging Tools

Tool	Icon	Description
Run		Execute the VI
List Errors		List errors that prevent the VI from running
Run Continuously		Execute the VI continuously until abort or pause is pressed
Stop		Stop VI execution immediately
Execution Highlighting		Animate data movement on the block diagram wires
Pause		Temporarily stop execution to debug a portion of the VI
Step Into		Single-step into a subVI or structure to debug it
Step Over		Execute a subVI or structure and resume single-stepping in next main function
Step Out		Execute a subVI or structure and resume single-stepping in calling VI or structure

### Tools Palette

Tool	Icon	Description
Automatic Tool Selection		Automatically choose the appropriate tool
Operating Tool		Change the value of a control or select the text within a control
Positioning Tool		Position, resize, and select objects
Labeling Tool		Edit text and create free labels
Wiring Tool		Wire objects together on a block diagram
Scroll Tool		Scroll the window without using the scroll bars
Breakpoint Tool (used for debugging)		Set breakpoints on VIs, functions, wires, loops, sequences, and cases
Probe Tool (used for debugging)		Create probes on wires and display intermediate values on a wire in a running VI
Color Copy Tool		Copy colors for pasting with the Color Tool
Color Tool		Set the foreground and background colors



# Setup Resources

- [Learn LabVIEW—Video Training](#)
- [LabVIEW Environment Overview](#)
- [Creating Custom Controls](#)
- [LabVIEW Dataflow](#)
- [LabVIEW Tools](#)
- [LabVIEW Data Structures](#)
- [LabVIEW Debugging](#)
- [WPI Library Overview](#)
- Forum Support (year round)
  - [ni.com/frc](https://ni.com/frc)
- Phone Support (during build season only)
  - (866) 511-6285 from 1:00 to 7:00 pm (Central Time)

All links available  
at  
[ni.com/frc](https://ni.com/frc) or  
click this button

